

Nic VIRTUAL SuseLinux Server werkt niet

Omschrijving:



Na het clonen van een SLES VM is de netwerkkaart niet te connecteren met het netwerk.
Ook niet bij het aanmaken van een nieuwe Nic.




Bij een IFCONFIG -a is de netwerkkaart wel te zien maar heeft geen IP adres of subnetmask.
Maar wel een macadres

Oorzaak:

SLES kent een verkeerd macadres/name toe aan de virtuele netwerkkaart

Oplossing:

	Klik op Computer / Yast / Network Devices / Networkcard
	Klik op next

	Configureer de Nic met de benodigde gegevens: - ip adres - Hostname - DNS - Gateway Herstart de sles server !
Herstart SLES server 	Login in op de SLES server en noteer via een ifconfig het macadres van de ethernet card In dit geval 00:50:56:a8:61:30
	Klik weer op Computer / Yast / Network Devices / Networkcard Verwijder de network card ! en herstart de server (voor alle zekerheid)
Herstart SLES server	

YaST2@gegevensmag-test Network Card Overview Network Card Overview Overview of network cards. Edit their configuration. Add a Network Card: Click to configure a new network card manually. or Deleting: Click to remove a network card to or remove. Then click Edit or Delete as Network Card Configuration Overview Name IP Address AMD PCnet - Fast 79C971 Not configured AMD PCnet - Fast 79C971 The device is not configured Press Edit to configure Add Edit Delete Network Address Setup General Address Device Type Ethernet Configuration Name bus-pci-0000:00:11:0 ☐ None Address Setup ☒ Automatic Address Setup (via DHCP) ☐ Static Address Setup IP Address Subnet Mask 255.255.255.0 Detailed Settings Hostname and Name Server Routing Advanced ... Klik weer op Computer / Yast / Network Devices / Networkcard Edit nu de network card Voer bij de Configuraton Name de volgende gegevens handmatig in: Eth-id-00:50:56:a8:61:30 Configureer de network card af via static address setup - ip adres - Subnetmask Hostname and Name Server - Hostname - DNS Routing - Gateway

YaST2@gegevensmag-test

Network Card Overview

Obtain an overview of installed network cards. Additionally, edit their configuration.

Adding a Network Card:
Press **Add** to configure a new network card manually.

Editing or Deleting:
Choose a network card to change or remove. Then press **Edit** or **Delete** as desired.

Network Card Configuration Overview

Name	IP Address
AMD PCnet - Fast79C971	172.16.1.131

AMD PCnet - Fast79C971

- Device Name: eth-eth-id-00:50:56:a8:61:30
- Started automatically at boot
- IP address: 172.16.1.131, subnet mask 255.255.0.0

Add

Edit

Delete

Back

Abort

Finish

Modem

Hi

iS

Pt

Rt

Vt

Vt

IS

Nt

Klik op Finished en herstart de SLES server.

Nadat deze herstart is, zal de network card wel een connectie hebben met het netwerk.